

1917 • SMC select ROSAS

Size	XS	S	M	L	XL
Front and Back					
Width	15¾" [40cm]	17¼" [44cm]	19" [48cm]	21¼" [54cm]	23½" [60cm]
Armhole width	2¼" [6cm]	2¾" [7cm]	3¼" [8cm]	3½" [9cm]	4¼" [11cm]
Armhole depth	6¼" [16cm]	7" [18cm]	7¾" [20cm]	8¼" [21cm]	9" [23cm]
Neck width	8¾" [22cm]	8¾" [22cm]	8¾" [22cm]	9" [23cm]	9½" [24cm]
Neck depth, back	6" [15cm]	6" [15cm]	6" [15cm]	6" [15cm]	6" [15cm]
Neck depth, front	7¾" [20cm]	7¾" [20cm]	7¾" [20cm]	7¾" [20cm]	7¾" [20cm]
Shoulder width	1¼" [3cm]	1½" [4cm]	2" [5cm]	2¼" [6cm]	2¾" [7cm]
Total length	21¼" [54cm]	21¼" [54cm]	22" [56cm]	22½" [57cm]	22¾" [58cm]


Ladie's Top

Instructions are given for first size. Figures in parenthesis refer to larger sizes. When only one figure is given, it applies to all sizes.

Materials: approx. 5 (6, 7, 8, 8) balls (approx. 88yd/80m each) of SMC select **Rosas** (55% polyamide, 45% cotton) in col 01704 beige.

Size 8-10 [5-6mm] needles.

Moss Stitch: row 1: k1, p1; row 2: k the k sts, p the p sts; row 3: p1, k1; row 4: rep row 2; rep rows 1-4 throughout.



Gauge: 17 sts and 30 rows = 4" [10 cm] in moss st.

Back: cast on 70 (78, 84, 94, 104) and work in moss st until back measures 15 (14¼, 14¼, 13¾)" [38 (36, 36, 35) cm]. Shape armholes: bind off 4 (5, 6, 8, 10) sts at beg of next 2 rows, 3 sts at beg of foll 2 rows, 2 sts at beg of foll 2 rows and 1 st at beg of foll 2 (4, 6, 6, 8) rows – 50 (54, 56, 62, 66) sts.

Cont in pat as established until back measures 15¼ (15¼, 16¼, 16½, 17)" [39 (39, 41, 42, 43) cm]. Shape neck: work to center 10 (10, 10, 12, 14) sts, join another ball of yarn, bind off center 10 (10, 10, 12, 14) sts, work to end. Working both sides at same time, bind off 3 sts at each neck edge once, 2 sts twice and 1 st twice.

When back measures 21¼ (21¼, 22, 22½, 22¾)" [54 (54, 56, 57, 58) cm], bind off remaining 7 (9, 10, 12, 13) sts for each shoulder.

Front: work same as for back until front measures 13½ (13½, 14¼, 14½, 15)" [34 (34, 36, 37, 38) cm]. Shape neck same as for back and when same length as back to shoulders, bind off remaining 7 (9, 10, 12, 13) sts for each shoulder.



Finishing: pin pieces to measurements and block with damp towels. Sew shoulder and side seams.